Video Player QA Test Plan

Video Player QA Test Plan

Environments

Unable to render {include}

The included page could not be found.

General QA Guidelines

General Use

- Does the tool behave the way that you would expect?
- Are you surprised by anything?
- Does something take longer than you would expect?
- When the tool does something unexpected or takes too long to do something, does the tool
 provide appropriate feedback?

On This Page

- QA Tests
 - Unit Test
 - Manual Tests
 - Mouse Functionality
 - Page Load, Basic Play/Pause
 - Controls: Play Button
 - Controls: Volume Controls
 - Controls: Caption Controls
 - Controls: Transcript Controls
 - Controls: Scrubber Bar
 - Transcript Navigation
 - Controls: Full-Screen Controls
 - Keyboard Functionality
 - Keyboard Play/Pause
 - Keyboard Controls: Play Button
 - Keyboard Controls: Volume Controls
 - Keyboard Controls: Caption Controls
 - Keyboard Controls: Transcript Controls
 Keyboard Controls: Scrubber Bar
 - Keyboard Transcript Navigation
 - Keyboard Controls: Full-Screen Controls

Specification

- (Floe) video player mockups (final)
- (Floe) video player interactions

QA Tests

Protocol

Perform the following tests using each browser/system environment. Report issues at: http://issues.fluidproject.org/secure/Dashboard.jspa



Please search for issues before reporting them, so as to limit the number of duplicate entries: Video Player JIRA Filter

Currently known issues are indicated on this page by their JIRA number.

- If you note during your testing that an issue has been resolved, please edit this page and remove the JIRA number.
- . If you file a JIRA for a new issue, please edit this page and add the JIRA number beside the relevant 'expected result.'

Unit Test

Protocol

Launch the following website to execute unit tests.

Video Player Test Suite:

http://build.fluidproject.org/videoPlayer/videoPlayer/tests/all-tests.html

Manual Tests

 $\underline{\text{Description}}_{\text{Ensures that the component properly functions on the aspects that are not covered by the integration test.}$

 $\frac{\text{Protocol}}{\text{Perform these tasks on the following site, perform the tests in order.}}$

Video player sample: One video player per page Multiple video players per page

Mouse Functionality

Page Load, Basic Play/Pause

Procedure	Expected Results
Load the "One video player per page" demo in a browser window.	 Page should show video player container. Video should not play automatically. Video player container should show a symbol overlay. FLUID-4599 Control menu should not be visible. Transcript area should not be visible. Captions should not be displayed.
Using the mouse, hover over the video player.	 On hover, the scrubber bar and control buttons should appear. Play symbol overlay should not disappear. FLUID-4599
Move the mouse away from the video player.	 Scrubber bar and control buttons should disappear. FLUID-4652 Play symbol overlay should remain. FLUID-4599
Click somewhere in the centre of the video area. Leave the cursor over the video area.	 Play symbol overlay should disappear. Video should play. Play symbol on the Play/Pause button at the left end of the control buttons should change to a Pause symbol.
Click again somewhere near the centre of the video area	 Video should stop playing. Play symbol overlay should NOT re-appear. VP-273 Pause symbol on the Play/Pause button at the left end of the control buttons should change to a Play symbol.

Controls: Play Button

Procedure	Expected Results
Move the mouse cursor over the video; controls will appear. Hover over the Play button.	 Play button should get a darker background. Tooltip containing "Play" should appear near the Play button.
Click on the Play button. Keep mouse positioned over the button.	 Video should play. Play button should change to a Pause button. Tooltip text should change to contain "Pause".
Click the Pause button.	 Video should stop playing. Pause button should change to a Play button. Tooltip should change to contain "Play."
Click the Play button.	 Video should resume playing where it was paused. Play button should change to a Pause button. Tooltip text should change to contain "Pause".

Controls: Volume Controls

Procedure	Expected Results
Move the mouse cursor over the video; controls will appear. Hover over the Volume button.	 Volume button should get a darker background. Vertical volume slider at should appear above Volume button. Slider thumb should be at roughly 50%. Slider under the thumb should be a different colour than the slider above the thumb. Tooltip containing "Volume" should appear near the Volume button. FLUID-4859
Click the Volume button. Keep mouse positioned over the button.	 Volume button should change to a Muted button (speaker symbol with an X). Slider thumb should drop to bottom. Tooltip should remain unchanged. Should say "Volume". FLUID-4859
Click the Volume button again. Keep mouse positioned over the button.	 Muted button should change to back a Volume button). Slider thumb should return to original position. Tooltip should not change. Should say "Volume". FLUID-4859
Use the mouse to drag the volume slider thumb control up or down.	The colours above and below the thumb should continue to fill the available space.
Slide the Volume slider up almost to the top of the slider. Click the Volume button to mute. Click the Volume button again to un-mute.	 While muted, the volume slider thumb should drop to the bottom. Once un-muted, the volume slider should return to where you left it, near the top of the slider.
Slide the Volume slider all the way to the bottom of the slider.	Volume button should change to a Muted button (speaker symbol with an X).
Slide the Volume slider up away from the bottom of the slider.	Muted button should change back to a Volume button.
Start the video playing (either by clicking in the video area or on the Play button). While listening to the audio, slide the Volume slider up and down.	The volume of the video should be raised and lowered according to the slider.

Pause the video.

Controls: Caption Controls

Procedure	Expected Results
Move the mouse cursor over the video; controls will appear. Hover over the Caption (CC) button.	 Caption button should get a darker background and "CC" should appear inverted (light text on dark background). Tooltip containing "Captions" should appear near the Captions button.
Click the Caption (CC) button	 The caption menu should appear above the button. The Caption menu should include a list of languages (English and French) and a "Show Caption" option at the bottom of the menu. The English menu item should be bolded.
Click the Caption button again.	The caption menu should disappear.
Click the Caption button again.	The caption menu should reappear.
Click the "Show Captions" menu item.	 The caption menu should disappear. The Captions button should switch to orange on a darker background. An overlay should appear briefly confirming that captions are turned on, then disappear. The overlay should mention the current language, English. FLUID-4601
Play the video	English captions should appear, synchronized to the audio.
Click the Captions button and select French.	 Caption should continue to display, but should switch to French captions. An overlay should appear briefly confirming the new language choice, French (and that captions are on) then disappear. FLUID-4601

Click the Captions button and select "Hide Captions"	 The caption menu should disappear. The captions should disappear. The "CC" symbol should return to dark grey text on lighter grey background. An overlay should appear briefly confirming that captions are turned off, then disappear. The overlay should mention the current language, French. FLUID-4601 	
Click the Captions button and select "English"	 The caption menu should disappear. English captions should display with the video. An overlay should appear briefly confirming that captions are turned on, then disappear. The overlay should mention the current language, English. FLUID-4601 	

Pause the video and reload the page.

Controls: Transcript Controls

Procedure	Expected Results
Move the mouse cursor over the video; controls will appear. Hover over the Transcripts button.	Transcripts button should get a darker background. Tooltip containing "Transcripts" should appear near the Transcripts button.
Click on the Transcript button	 The transcript menu should appear above the button. The Transcript menu should include a list of languages (English and French) and a "Show Transcript" option at the bottom of the menu. The English menu item should be bolded.
Click the Transcript button again.	The transcript menu should disappear.
Click the Transcript button again.	The transcript menu should reappear.
Click the "Show Transcripts" menu item.	 The transcript menu should disappear. The transcript area should appear to the right of the video area, containing English transcripts. The icon in the Transcripts button should switch to orange.
Click the Transcript button and select French.	Content of transcript area should switch to French transcripts.
Click the Transcript button and select "Hide Transcript"	 The transcript menu should disappear. The transcript area should disappear. The icon in the Transcripts button should switch to back to white.
Click the Transcript button and select "English"	The transcript menu should disappear. The transcript are should appear on the right, containing English transcripts.

1 Todo:

- Change transcript languageOpen and close using "X" button.

Controls: Scrubber Bar

Procedure	Expected Results
Move the mouse cursor over the video; controls will appear. Use the Captions button to show captions. Use the Transcripts button to show transcripts. Click anywhere in grey area of scrubber bar.	 From the beginning of the scrubber bar to where the click happens, the background color turns yellow. The start time on the time box gets updated to a reasonable new time reflecting the click location. The video jumps to another clip reflecting the click location. The caption shows up with the text that's associated with the new video clip. The transcript text scrolls to the transcript text that's associated with the new video clip.
Click elsewhere in the scrubber bar; try different locations.	The results described above should always happen, adjusted to be relevant to the correct spot in the timeline.

Transcript Navigation

Procedure	Expected Results
Reload page	
Move focus to the video player.	 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Activate and show English Transcripts	 The transcript menu should disappear. The transcript area should appear to the right of the video area, containing English transcripts. The icon in the Transcripts button should switch to orange.
Hover over "David Kelleyhuman centered" in the transcript.	The text "David Kelleyhuman centered" should appear blue.
Select "David Kelleyhuman centered"	 "David Kelleyhuman centered" should now be white text on blue background. Yellow progress bar should appear on the left of the timeline. Timecode thumb should say "0:18/5:43". Image in video player should show text "David Kelley says Most experts agree." and an image of Mr. Kelley on a YouTube video. Video should not be playing.
Press the play button on the video player	Video should start playing from 0:18
With video still playing, select transcript text below the text currently being played.	The video and audio should jump to the position with the corresponding selected text. Time code should change respectively. The video progress bar should change respectively.

Controls: Full-Screen Controls

Procedure	Expected Results
Reload the page	
Move the mouse cursor over the video; controls will appear. Hover over the Full-screen button.	 Full-screen button should get a darker background. Tooltip containing "Full screen" should appear near the Full-screen button.
Click the Full-screen button	 The video should switch into full-screen mode. The video controls should be visible along the bottom of the screen. The Full-screen button icon should switch to a 'small-screen' icon. A message that states "Press ESC to return to exit full screen" (or similiar) should appear along the top.
Do not move the mouse or press any keys for a short time.	The controls should disappear.
Move the mouse.	The controls should reappear.
Test the mouse functionality as described above: Play / pause Volume Captions	All controls should function as they would in non-full-screen mode. Example: Tooltips appear properly Button colours change according to state Controls work as expected Positioning and rendering appears correct etc.
Play the video	 Video should play. Play button should change to a Pause button. Tooltip text should change to contain "Pause".

While video is playing, click the Full-screen button again.	The video should switch back to its original size. Video should continue playing during this transition
Stop video and click the Full-screen button again.	 The video should stop playing. switch into full-screen mode again. remain in a stopped state controls visible, with "ESC to exit full screen" message at top
Press the Escape key.	The video should switch back to its original size.

Keyboard Functionality

Keyboard Play/Pause

Procedure	Expected Results
Load the "One video player per page" demo in a browser window.	 Page should show video player container. Video should not play automatically. Video player container should show a symbol overlay. FLUID-4599 Control menu should not be visible. Transcript area should not be visible. Captions should not be displayed.
Using only the Tab key on the keyboard, move focus to the video player.	When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Press the Space key.	 Play symbol overlay should disappear. FLUID-4599 Video should start playing. Play button should turn into a Pause button.
Press the Space key again.	 Play symbol overlay should not reappear. FLUID-4599 Video should stop playing. Pause button should turn into a Play button.
Press Space key	 Play symbol overlay should not reappear. FLUID-4599 Video should stop playing. White on Blue background pause button should be replaced by a play button.
Repeat the above-mentioned Play/Pause tests using the Enter key instead of Space.	Results should be the same.

Reload the page.

Keyboard Controls: Play Button

Procedure	Expected Results
Reload the page	
Using only the Tab key on the keyboard, move focus to the video player.	When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Press Tab once more.	 The controls should appear. FLUID-4785 The Play button should appear white on a blue background. Play symbol overlay should not disappear. FLUID-4599

Press Space key	 Play symbol overlay should disappear. FLUID-4599 Video should start playing. Play button should turn into a Pause button. Pause button should appear as white on blue background. Tooltip should change to say "Pause" FLUID-4743
Press Space key	 Play symbol overlay should not reappear. FLUID-4599 Video should stop playing. White on Blue background pause button should be replaced by a play button. Tooltip should change to say "Play" FLUID-4743
Repeat the above-mentioned Play/Pause tests using the Enter key instead of Space.	Results should be the same.

Reload the page.

Keyboard Controls: Volume Controls

Expected Results
 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
 The controls should appear. FLUID-4785 The Volume button should appear white on a blue background. Volume slider should appear vertically above the volume button. Slider thumb should be at roughly 50%. Slider under the thumb should be a different colour (i.e. yellow) than the slider above the thumb (i.e. white). Tooltip should say "Volume". FLUID-4859
*The volume slider should move down. *Yellow colour under the slider should decrease while white colour above slider should increase.
*The volume slider should move up. *Yellow colour under the slider should increase while white colour above slider should decrease.
 Volume button should change to a Muted button (speaker symbol with an X). Slider thumb should drop to bottom. Tooltip should say "Volume". FLUID-4859
 Muted button should change to back a Volume button. Slider thumb should return to original position. Tooltip should not change and should still say "Volume". FLUID-4859
 While muted, the volume slider thumb should drop to the bottom. Once un-muted, the volume slider should return to where you left it, near the top of the slider.
Volume button should change to a Muted button (speaker symbol with an X).
Muted button should change back to a Volume button.
The volume of the video should be raised and lowered according to the slider.

Procedure	Expected Results
Reload the page.	
Using only the Tab key on the keyboard, move focus to the video player.	 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Press Tab four more times.	 The controls should appear. FLUID-4785FLUID-4863 Caption button should get a darker background and "CC" should appear inverted (light text on dark background). Tooltip containing "Captions" should appear near the Captions button. Play symbol overlay should not disappear. FLUID-4599
Activate the Caption (CC) button by pressing Space or Enter	 The caption menu should appear above the button. The Caption menu should include a list of languages (English and French) and a "Show Caption" option at the bottom of the menu. The English menu item should be bolded.
Deactivate the Caption (CC) button by pressing Space or Enter again.	The caption menu should disappear.
Activate the Caption (CC) button by pressing Space or Enter again.	The caption menu should reappear.
Activate the "Show Captions" menu item.	 The caption menu should disappear. The Captions button should switch to orange on a darker background. An overlay should appear briefly confirming that captions are turned on, then disappear. The overlay should mention the current language, English. FLUID-4601
Play the video by shift-tabbing back to the Play button, or by tabbing until the video player is focused and pressing Enter/Space.	English captions should appear, synchronized to the audio.
Tab back to Captions Activate the Captions button and select French.	 Caption should continue to display, but should switch to French captions. An overlay should appear briefly confirming the new language choice, French (and that captions are on) then disappear. FLUID-4601
Click the Captions button and select "Hide Captions"	 The caption menu should disappear. The captions should disappear. The "CC" symbol should return to dark grey text on lighter grey background. An overlay should appear briefly confirming that captions are turned off, then disappear. The overlay should mention the current language, French. FLUID-4601
Activate the Captions button and select "English"	 The caption menu should disappear. English captions should display with the video. An overlay should appear briefly confirming that captions are turned on, then disappear. The overlay should mention the current language, English. FLUID-4601

Keyboard Controls: Transcript Controls

Procedure	Expected Results
Reload page	
Using only the Tab key on the keyboard, move focus to the video player.	 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Press Tab five more times.	 The controls should appear. FLUID-4785FLUID-4863 Transcript button should get a darker background and transcript icon should appear inverted (light text on dark background). Tooltip containing "Transcripts" should appear near the Transcript button. Play symbol overlay should not disappear. FLUID-4599

Activate the Transcript button by pressing Space or Enter	 The transcript menu should appear above the button. The Transcript menu should include a list of languages (English and French) and a "Show Transcript" option at the bottom of the menu. The English menu item should be bolded.
Activate the Transcript button again.	The transcript menu should disappear.
Activate the Transcript button again.	The transcript menu should reappear.
Activate the "Show Transcripts" menu item.	 The transcript menu should disappear. The transcript area should appear to the right of the video area, containing English transcripts. The icon in the Transcripts button should switch to orange.
Activate the Transcript button and select French.	Content of transcript area should switch to French transcripts.
Activate the Transcript button and select "Hide Transcript"	 The transcript menu should disappear. The transcript area should disappear. The icon in the Transcripts button should switch to back to white.
Activate the Transcript button and select "English"	 The transcript menu should disappear. The transcript are should appear on the right, containing English transcripts.

1 Todo:

- Change transcript languageOpen and close using "X" button.

Keyboard Controls: Scrubber Bar

Procedure	Expected Results
Reload page	
Using only the Tab key on the keyboard, move focus to the video player.	 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Using only the keyboard, activate and show English Captions	 The caption menu should disappear. The Captions button should switch to orange on a darker background. An overlay should appear briefly confirming that captions are turned on, then disappear. The overlay should mention the current language, English. FLUID-4601
Using only the keyboard, activate and show English Transcripts	 The transcript menu should disappear. The transcript area should appear to the right of the video area, containing English transcripts. The icon in the Transcripts button should switch to orange.
Using only the Tab key, tab until the scrubber bar is in focus.	 Timecode scrubber thumb appears blue with white text and white border. Time should say: "0:00/5:43"
Press and hold the right arrow key for 3 seconds.	The timecode scrubber should move steadily to the right. The start time on the time box gets updated to a reasonable new time reflecting the click location. The video image changes reflecting the changing time / location. The caption shows up with the text that's associated with the new video clip. The transcript text scrolls to the transcript text that's associated with the new video clip.
Press and hold the Left or right arrow key to go back and forward on the timeline.	The results described above should always happen, adjusted to be relevant to the correct spot in the timeline.

Procedure	Expected Results
Reload page	
Using only the Tab key on the keyboard, move focus to the video player.	When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Using only the keyboard, activate and show English Transcripts	 The transcript menu should disappear. The transcript area should appear to the right of the video area, containing English transcripts. The icon in the Transcripts button should switch to orange.
Press Tab 4 more times	Blue outline should appear around "Eeny, meeny,miny,moe"
Press Down Arrow 7 times	Blue outline should appear around "David Kelleyhuman centered".
Press Enter	 "David Kelleyhuman centered" should now be white text on blue background. Yellow progress bar should appear on the left of the timeline. Timecode thumb should say "0:18/5:43". Image in video player should show text "David Kelley says Most experts agree." and an image of Mr. Kelley on a YouTube video. Video should not be playing.
Using only the tab button, tab until the video player has focus.	 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not appear. FLUID-4599 The controls should not appear. FLUID-4785
Press Enter on the Video Player	Video should start playing from 0:18
With video still playing, press tab 4 times	Blue focus outline should appear around the string of text currently being played.
Press down arrow 4 times	A blue outline should appear around the 4th selectable item below the string of text being played.
Press Enter key	The video and audio should jump to the position with the corresponding selected text. Time code should change respectively. The video progress bar should change respectively.
Press the down arrow key until the selected text is well "below the fold". Wait a moment for the video to progress.	Focus should remain on the selected text and not shift to the text currently being spoken.

Keyboard Controls: Full-Screen Controls

Procedure	Expected Results
Reload the page	
Using only the Tab key on the keyboard, move focus to the video player.	 When tab focus arrives at the video player, the video area should show a blue border around it. Play symbol overlay should not disappear. FLUID-4599 The controls should not appear. FLUID-4785
Press Tab key 7 times	 Focus should appear on the full screen button. Button should appear white on blue. Tool tip "Full screen" should appear.

Press Enter.	The video should switch into full-screen mode. The video controls should be visible along the bottom of the screen. The Full-screen button icon should switch to a 'small-screen' icon. A message that states "Press ESC to return to exit full screen" (or similiar) should appear along the top.
Do not move the mouse or press any keys for a short time.	The controls should disappear.
Press Space bar or Enter	The video should start playing. Time bar should advance.
Press and hold Up arrow	The volume should increase.
Press and hold Down arrow	The volume should decrease.
Press Space bar or Enter	The video should stop playing.
Press Tab key.	The controls should reappear. Focus should be on the Play button. Play button should appear
Test the keyboard functionality as described above: Play / pause Volume Captions Transcripts	All controls should function as they would in non-full-screen mode. Example: Tooltips appear properly Button colours change according to state Controls work as expected Positioning and rendering appears correct etc.
Press tab until focus is back on the Play button. Play the video.	 Video should play. Play button should change to a Pause button. Tooltip text should change to contain "Pause".
While video is playing, press tab until the exit full-screen button is in focus. *Activate the exit full-screen button.	The video should switch back to its original size. Video should continue playing during this transition
Press Enter or Space to stop video and activate the Full-screen button again using keyboard only.	 The video should stop playing. switch into full-screen mode again. remain in a stopped state controls visible, with "ESC to exit full screen" message at top
Press the Escape key.	The video should switch back to its original size.