

# FSS Text - Font size

## Error rendering macro 'html'

Your Confluence administrator has disallowed the use of Javascript in the HTML macro. This setting can be changed using HTML for Confluence Configuration. Please see your administrator for details.

**NOTE:** FSS is deprecated as of 1.5

<b>All Text Examples</b>
<a href="#">Font size</a>
<a href="#">Font family</a>
<a href="#">Letter spacing</a>
<a href="#">Text alignment</a>
<a href="#">Colours and Highlight colours</a>
<a href="#">Styles</a>

**NOTE:** FSS is deprecated as of 1.5

<b>FSS Documentation</b>
<a href="#">Fluid Skinning System - FSS</a> <a href="#">FSS Naming Conventions</a> <a href="#">FSS Cheat Sheet</a> <a href="#">Mobile FSS Cheat Sheet</a>  <a href="#">Demos: Columns</a> <a href="#">Demos: Tabs, Menus, etc.</a> <a href="#">Demos: Text</a> <a href="#">Demos: Themes</a>  <a href="#">HTML and CSS Background</a> <a href="#">CSS Bugs, Gotchas</a>

<b>Still need help?</b>
Join the <a href="#">infusion-users mailing list</a> and ask your questions there, or hang out in our <a href="#">IRC Channel</a> .

## Font Size

(Note that other sizes are also available. See the [FSS Cheat Sheet](#) for specifics.)

This paragraph is adjusted to 70% of regular size.

This paragraph is adjusted to 100% of regular size.

This paragraph is adjusted to 120% of regular size.

This paragraph is adjusted to 150% of regular size.

The markup and classes used to produce this example:

```
<p class="fl-font-size-70">This paragraph is adjusted to 70% of regular size.</p>
<p class="fl-font-size-100">This paragraph is adjusted to 100% of regular size.</p>
<p class="fl-font-size-120">This paragraph is adjusted to 120% of regular size.</p>
<p class="fl-font-size-150">This paragraph is adjusted to 150% of regular size.</p>
```

NOTE: The `fl-font-size-*` classes are applied to the paragraph tags and so apply only that paragraph. The class could be applied to a `<div>` surrounding many paragraphs to apply the style to all paragraphs.